

DUMP

The DUMP command is used for diagnostic purposes. When issued, it formats and prints the contents of the requested storage to SYSLST.

Syntax: DUMP {ALL|BUFFers|BUS|CONnects|DIRectory|Events|FRAGments|FREquests|FTPds|GIVesockets|GPSds|HTTpds|IVBlok|LINKs|LPDs|MASKs|MENus|NAMes|PROGrams|ROUtes|SOCKets|STATs|TASKs|TCBs|TELnetds|TLSds|TRACes|TRANslations|USERs|VERsions}

Arguments:

ALL	- All eligible areas will be dumped. This option will require a lot of CPU and spool space.
BUFFers	- The pooled Telnet buffers are dumped.
BUS	- The data bus (IBBLOKs) is dumped.
CONnects	- Connection control blocks are dumped.
DIRectory	- The file system directory blocks are dumped.
Events	- Currently queued automation Event Blocks are dumped.
FRAGments	- Datagrams fragments currently being processed are dumped.
FREquests	- In-flight file I/O requests are dumped.
FTPds	- Control blocks belonging to FTP Daemons are dumped.
GIVesockets	- The GiveSocket queue is dumped.
GPSds	- Control blocks belonging to GPS Daemons are dumped.
HTTpds	- Control blocks belonging to HTTP Daemons are dumped.
IVBlok	- The Internal Vector Block is dumped.
LINKs	- Link driver control blocks are dumped.
LPDs	- LPD control blocks are dumped.
MASKs	- The masks created by DEFINE MASKS are dumped.
MENus	- TelnetD menus are dumped.
NAMes	- Blocks created by DEFINE NAME are dumped.
PROGrams	- Loaded programs will be dumped.
ROUtes	- The routing table is dumped.
SOCKets	- Currently-allocated socket blocks are dumped.
STATs	- The content of the statistics table is dumped.
TASKs	- The pseudo task control blocks are dumped.
TCBs	- The Task Control Blocks belonging to the VSE subtasks are dumped.
TELnetds	- Control blocks belonging to Telnet Daemons are dumped.
TLSds	- Control blocks belonging to TLS Daemons are dumped.
TRACes	- Dumps the content of all currently-running DEFINE TRACE and DEFINE SOTRACE commands.
TRANslations	- The translate tables are dumped.
USERs	- User blocks, as created by DEFINE USER, are dumped.
VERsions	- The versions table is dumped.

Example:

```
IPN237I dump users
IPN206I Dump has completed
```

Notes: • Except for DUMP TRACES, output from the DUMP command is of little use to the installation.

DUMP *(continued)*

In general, you should use this command only when Technical Support asks you to.

- Regardless of log settings, the DUMP command never sends data to the console.
 - Output from the DUMP command can be voluminous. *TCP/IP for VSE* processing is likely to be impacted during the dump.
-

Related	DEFINE SOTRACE	- Start a Socket Trace.
Commands:	DEFINE TRACE	- Start a Datagram Trace
	QUERY TRACES	- Displays a list of currently-running traces.
