

QUERY PROGRAMS

The QUERY PROGRAMS command allows you to view information about the various phases being used to provide TCP/IP and related services.

Syntax: Query PROGrams [,SYSLst]

Arguments: SYSLst - If specified, the results of this request are sent to SYSLST. If omitted, the results are displayed on the console.

Example:

```
IPN237I query programs
IPN253I << TCP/IP Phases and Routines >>
IPN636I  FTPDAEMN  00604050  02E250  80604050  SYST  RENT  PRODLIB.PHASE
IPN636I  IPDSLIBR  005F6050  000958  805F6050  SYST  RENT  PRODLIB.PHASE
IPN636I  IPTRLOAD  005103A0  0026F1  00000000  SYST  RENT  PRODLIB.PHASE
IPN636I  ASOCKET   00319000  0011A8  80319020  SYS   SVA   PRODLIB.PHASE
IPN636I  CLIENTD   00633050  011F78  80633050  0020          PRODLIB.PHASE
IPN636I  CSOCKET   0361F050  002D98  8361F050  SYS          PRODLIB.PHASE
IPN636I  IOAPPEND  002E60F0  000460  802E60F0  SYS   SVA   PRODLIB.PHASE
IPN636I  IPCCSERV  0361A050  002AE8  8361A050  SYS          PRODLIB.PHASE
IPN636I  IPNCICMP  0354A050  001600  8354A050  0013          PRODLIB.PHASE
IPN636I  IPNCOCMP  03552850  000540  83552850  0014          PRODLIB.PHASE
IPN636I  IPNETAS   005AD050  000B00  805AD050  SYS          PRODLIB.PHASE
IPN636I  IPNFLIBR  005BC050  016D20  805BC050          PRODLIB.PHASE
IPN636I  IPNFPWR   005B2050  009788  005B2050          PRODLIB.PHASE
IPN636I  IPNFRX    005D3050  0011E8  805D3050          PRODLIB.PHASE
IPN636I  IPNIRAW1  03558050  000F50  83558050  0007          PRODLIB.PHASE
IPN636I  IPNIRAW2  03556050  001848  83556050  0008          PRODLIB.PHASE
IPN636I  IPNIVFGH  03627050  004A60  83627050  SYS          PRODLIB.PHASE
IPN636I  IPNLIIEE   03549850  0004B0  83549850  0017          PRODLIB.PHASE
IPN636I  IPNLOEEE   03549050  000450  83549050  0018          PRODLIB.PHASE
IPN636I  IPNL127    03647850  000680  83647850  0002          PRODLIB.PHASE
IPN636I  IPNRBSDC  044852D0  014D30  844892B0  SYS   SVA   PRODLIB.PHASE
IPN636I  IPNROUTE  03622050  001288  83622050  SYS          PRODLIB.PHASE
IPN636I  IPNTITCP   0354E050  001AD8  8354E050  000F          PRODLIB.PHASE
IPN636I  IPSECURE   00595050  003260  00595050  SYS          PRODLIB.PHASE
IPN636I  LOCKMGRX  0052C050  004AB8  8052C050  SYS          PRODLIB.PHASE
IPN636I  LPD        03559050  00B1A0  83559050  0005          PRODLIB.PHASE
IPN636I  MSKELIP   03649050  0193E8  83649050  SYS          PRODLIB.PHASE
IPN636I  PRODKEYS   00525850  000310  00525850  SYS          PRODLIB.CONFIG
IPN636I  SOCKPASS  0361D050  001CD8  8361D050  SYS          PRODLIB.PHASE
IPN636I  SOCTRACE  03624050  002E08  83624050  SYS          PRODLIB.PHASE
IPN636I  VERCHECK   00522050  0036A0  00522050  SYS          PRODLIB.PHASE
```

Related Commands: QUERY VERSIONS - Displays the versions and maintenance levels of stack components.